

Naziv midlvera	Windows 32bit	Windows 64bit	
	32bit pkcs#11	32bit pkcs#11	64bit pkcs#11
AET SafeSign	C:\Windows\System32\setpkcs11.dll	C:\Windows\SysWOW64\setpkcs11.dll (vidi napomenu)	C:\Windows\System32\setpkcs11.dll
MUP RSID Card MW	C:\Program Files\MUP RS\Republic of Serbia ID Card Middleware\rsidp11_x86.dll	C:\Program Files\MUP RS\Republic of Serbia ID Card Middleware\rsidp11_x86.dll	C:\Program Files\MUP RS\Republic of Serbia ID Card Middleware\rsidp11_x64.dll
MUP TrustEdgeID	C:\Program Files\NetSeT\TrustEdgeID\netsetpkcs11_x86.dll	C:\Program Files\NetSeT\TrustEdgeID\netsetpkcs11_x86.dll	C:\Program Files\NetSeT\TrustEdgeID\netsetpkcs11_x64.dll
PKS TrustEdgeID (stari)	C:\Program Files\NetSeT\TrustEdgeID PKS\netsetpkcs11_x86.dll	C:\Program Files\NetSeT\TrustEdgeID PKS\netsetpkcs11_x86.dll	C:\Program Files\NetSeT\TrustEdgeID PKS\netsetpkcs11_x64.dll
TrustEdgeID (deljeni PKS/MUP/VS)	C:\Program Files\TrustEdgeID\netsetpkcs11_x86.dll	C:\Program Files\TrustEdgeID\netsetpkcs11_x86.dll	C:\Program Files\TrustEdgeID\netsetpkcs11_x64.dll
ESSqca PKCS11	C:\ESSQCA\pkcs11\IDPrimePKCS11.dll	C:\ESSQCA\pkcs11\IDPrimePKCS11.dll	C:\ESSQCA\pkcs11\IDPrimePKCS1164.dll
Nexus Personal	C:\Program Files\Personal\bin\personal.dll	C:\Program Files (x86)\Personal\bin\personal.dll	C:\Program Files (x86)\Personal\bin64\personal64.dll

Napomene

Na 64bitnoj Windows instalaciji Windows-on-Windows podsistem pri učitavanju AET SafeSign automatski vrši prepravku putanje pa uvek treba koristiti C:\Windows\System32\setpkcs11.dll

Instalacija novog deljenog TrustEdgeID uklanja pojedinačne PKS i MUP instalacije